

Bulletin



07th April 2014

Product Bulletin – PHD6 Firmware Update to Version 2.26

Regions Affected: Pacific, South East Asia, Korea & Japan, Taiwan

Dear Distribution Partners,

Firmware v2.26 is now available for the PHD6. Customers may download the new firmware from <http://www.honeywellanalytics.com/en-US/services/biodownloads/Pages/default.aspx>.

Effective 07th Apr, 2014, the PHD6 units will begin shipping from manufacturing with Firmware version 2.26.

And the cutoff S/N for PHD6 unit is “**534504634**”, as reference.

Firmware 2.26 addresses the following items:

- Support of the new CO-H 2CF Hydrogen resistant sensor (SN: 54-54-25)
- Modification of the upper voltage-drop limit to address vibrator self-test false failures
- Added ability for the customers to bypass the need to calibrate with 0% Oxygen before they are able to use replacement Oxygen sensors.

If you have any further questions please do not hesitate to contact your local Honeywell Analytics sales representative for additional details.

Thank you for your continued business and support.

Sincerely,

Happy Zhang
Portable Product - HAAP
Honeywell Analytics